

# Table of Contents

<b>Prusa Connect - Slack notifications setup</b> .....	3
Step 1 - Introduction .....	4
Step 2 - Slack channel setup .....	5
Step 3 - Creating a Slack App .....	6
Step 4 - Creating a webhook .....	6
Step 5 - Configuring the webhook .....	7
Step 6 - Prusa Connect settings .....	8
Step 7 - Setting up Notification types .....	9



# Prusa Connect - Slack notifications setup




[help.prusa3d.com/g536172](https://help.prusa3d.com/g536172)

Scan the QR code to display the latest version of this chapter.




### STEP 1 Introduction




- ◆ In the following steps, we will set up Prusa Connect to send notifications to your Slack messaging app.
- ◆ **Slack** is a collaboration and messaging platform that can be downloaded for free at <https://slack.com/> and runs on all major computer and phone platforms.
- ◆ If you're new to Slack; sign up, create and **set up a workspace** first. You can do so at Slack.com.

## STEP 2 Slack channel setup




- To get started, we need to select a **channel** where the notifications will be sent.
- If you've recently started using Slack and created a new workspace, a channel has also been automatically created.
- If you have been using Slack already, you have the option to either use an existing channel or create a new one.
  - To create a new channel, navigate to the left menu, click **More > Your organization > Channels**
  - Then, hit **Create a channel** and proceed to set it up.


## STEP 3 Creating a Slack App




- Visit <https://api.slack.com/apps> and select **Create an App**.
- Select **From scratch**.
- Add a **name** for your new App, select your **workspace** and hit **Create App**.

## STEP 4 Creating a webhook




- On the Basic Information page, open **Incoming Webhooks**
- Turn the **Activate Incoming Webhooks** option to **ON**
- Select **Add New Webhook to Workspace**
-  For more info about the Webhooks, visit: <https://api.slack.com/messaging/webhooks>

## STEP 5 Configuring the webhook




- 🟠 Select a channel you wish to receive the notifications to.
- 🟢 Click **Allow**.
- 🟠 **Copy** the newly created **webhook URL** to your clipboard.

## STEP 6 Prusa Connect settings



- 🛡️ Visit [Connect.Prusa3D.com](https://connect.prusa3d.com) site and make sure you're logged in.
- 🔔 Click the **Notifications (Bell icon)** in the top-right corner and go to **Settings**.
- 🔗 In the Channels setup section, select **Slack** tab.
- 📄 Paste the **Webhook URL** from the clipboard into the **Endpoint URL** window.
- 🟢 Click **Save new**.
- 🟠 After saving, a checkmark on the left should appear, and the initial test notification will be sent to confirm its functionality.

### STEP 7 Setting up Notification types



- 🟡 In the Notification settings, select all the notification types you want to receive on your Slack app.
- 🟢 Congratulations! You should now start receiving notifications about the ongoing prints through Slack.
- 🟠 If you're interested in delving deeper into Prusa printer remote control services, visit the Prusa Connect and PrusaLink explained article.



---

---

---

---

---

---

---

---

---

---



---

---

---

---

---

---

---

---

---

---



---

---

---

---

---

---

---

---

---

---

